



Pump Genius Multiplex V1.00 Application Information

Equipment: CFW500

Firmware Version: V3.50 or higher

WLP Software Version: V11.11 or higher

New Application Version: PGMPX_CFW500_en_V1_00.apl

Old Application Version: -

Document Number (Application Manual): 10008448885/00

Functional deviations in the old application version

- 1) There is not.

Changes in the new application version

- 1) The Pump Genius Multiplex application was implemented in the WLP software.



NOTE!

Appendix 1 shows how to import Pump Genius Multiplex application to WLP.

Appendix 1 – How to Import Application to WLP

- 1) In the WLP Ladder Programmer, in “Tools” menu, select the “Import Application to WLP” option;
- 2) Search “PGMPX_CFW500_en_V1_00.apl” archive and press “OK”;
- 3) The Pump Genius Multiplex application will be imported to WLP;
- 4) To select the application, in “Tools” menu, “Application” option, “CFW500”, “Create”, “Pump Genius”, select “Multiplex” option.