



Pump Genius Multipump V2.05 Application Information

Equipment: CFW500

Firmware Version: V2.06 or higher

WLP Software Version: V11.11 or higher

New Application Version: PGMPM_CFW500_en_V2_05.apl

Old Application Version: PGMPM_CFW500_en_V2_04.apl

Document Number (Application Manual): 10004314066 / 00

Functional deviations in the old application version

- 1) During start/stop Pump in Parallel the reference could stuck the speed reference on transition value.

Changes in the new application version

- 1) Fixed speed reference during transition of start/stop parallel pump.



NOTE!

Appendix 1 shows how to import Pump Genius Multipump application to WLP.

Appendix 1 – How to Import Application to WLP

- 1) In the WLP Ladder Programmer, in “Tools” menu, select the “Import Application to WLP” option;
- 2) Search “PGMPM_CFW500_en_V2_05.apl” archive and press “OK”;
- 3) The Pump Genius Multipump application will be imported to WLP;
- 4) To select the application, in “Tools” menu, “Application” option, “CFW500”, “Create”, “Pump Genius”, select “Multipump” option.